

SOFTWARE RELEASE NOTES



Product: XRS
Version: 1.7.1.0000

XRS Version 1.7.1.0000

note shows as version 1.71.0000 in the software version menu

FIXES

- Fixed some Turkish translations

XRS Version 1.7.0.0000

note shows as version 1.70.0000 in the software version menu

FEATURES

- Support new languages: Russian, Czech, Hungarian, Polish, and Turkish.
- Add menu item BACKLIGHT (ON/OFF).

When set to OFF, the backlight has the original behaviour, which is to stay on when in the menus, but off when scanning tags or key presses outside the menu.

When set to ON, the backlight is still always on when in the menus, but also comes on for 10 seconds when a tag is scanned or a key is pressed.

XRS Version 1.61.0000

CHANGES

- In USA and Cannada XRS can not scan tags when charging from AC.

XRS Version 1.60.0000

FEATURES

- Support duplicate ID check for all animals in the session.
- Support printing sessions to external printer vis Bluetooth and RS232.
- Support the display of Session Record Count in large font size. (Time removed)
- Change the display of Bluetooth connection.

- Disable the auto populating of VID with the last 6-digits of EID.
- The default VID (the last 6-digits of EID) no longer can be downloaded.

FIXES

- Updates to support new batteries.

XRS Version 1.52.0000

FIXES

- Fixed: Occasional issue that XRS is unable to connect to EziLink
- Fixed: Occasional issue that data in sessions may be corrupted
- Fixed: Occasional issue that record is duplicated when duplicate is enabled

XRS Version 1.51.0000

FEATURES

- Add ID3000 to list of devices that XRS auto connects to over Bluetooth.

FIXES

- Fixed: More accurate battery capacity indication.

XRS Version 1.50.0005

FIXES

- Fixed: Occasional incorrect display of a previously read tag (as a duplicate).

XRS Version 1.50.0000

FEATURES

- Add option to ignore 'Animal bit'.
- Add 'Animal not on list' feature.

FIXES

- Fixed: Bluetooth search did not timeout if no devices were found.
- Fixed: Tag was repeatedly output and saved to memory every 30 seconds if Read button held down.

XRS Version 1.44.0000

FIXES

- Fixed: Bluetooth could stop working if the XRS was turned on at the same time as an XR3000 or ID3000 with a Bluetooth dongle.

XRS Version 1.43.0000

FEATURES

- Bluetooth disabled when connected to EziLink™
- ® added to Bluetooth Icons and BLUETOOTH in menu
- Bluetooth auto connects to the Series 3000 Bluetooth dongle
- The Custom Field and Continuous Mode features can now work together
- Previously entered custom field data can be reviewed and changed if a duplicate tag is detected. Duplicate Tags will not increment the counters
- When connected to the XR3000 over Bluetooth if the XRS language is English (the default), it sets the XRS language to the language of the XR3000
- French and Spanish language strings updated

FIXES

- Fixed: Occasional premature low battery shutdown issue
- Fixed: Issue where user does not now have to start a new session to avoid the “Duplicate not saved message” on subsequent weighing sessions.
- Fixed: Corruption in session data count

XRS Version 1.21.0000

FEATURES

- Read Mode added to Setup Menu (previously could only be set in EziLink™)
- New mode added to Read Modes (Standard, Continuous, Single)
- After entering custom field data, pressing Read button starts scanning immediately

XRS Version 1.10.0002

- Major Release – original XRS firmware release